

# AliceStreet Conference Center

A **real** conference room on your desktop

## Quick Install

Version 1.6.535.0

January 18, 2007

**AliceStreet**  
Conference Center



© AliceStreet Inc. 2003 – 2007  
Specifications subject to change without notice  
1 of 3

USA    Canada    UK    South Africa    Australia    Brazil    Thailand    Caribbean  
[www.alicestreet.com](http://www.alicestreet.com)

## Quick installation instructions

### Install the server

- You will need a machine running a Windows family operating system to use as your AliceStreet server. We recommend an Intel processor with a speed of at least 3.0 GHz, and for optimal performance we recommend that this machine be dedicated only for use as the AliceStreet server.
- The server should be connected to your LAN/WAN prior to installation.
- Log on to the server with administrator rights
- Run the file ACCServerSetup.exe and follow the instructions
- **At the end of the installation restart the machine. After restarting, the AliceStreet server will start automatically**
- From a client, browse to the local server using: [http://\[host name\]](http://[host name]) and a window will open (Figure 1). This will verify the server install was successful. You can also check this by going to: [http://\[host name\]/about](http://[host name]/about)




Figure 1 – About window

- From a client, browse to the local server using: [http://\[host name\]/register](http://[host name]/register), and enter the licence number provided. The default user name is **admin** and the password is blank. Once registration is complete, and authenticated off AliceStreet's servers, click on the restart button displayed in the browser window. Please note your licence information after the restart.
- Please proceed to the AliceOnDemand instructions provided to you. You can test the operation of AliceStreet by: browsing to the local server using: [http://\[host name\]/meetings](http://[host name]/meetings), and enter the room names and associated passwords. Do not use punctuation marks in the meeting room names. See APP4 for more detailed instructions. Please be sure to delete the rooms you have manually set up prior to operation of AliceOnDemand.
- To uninstall the server, use Add/Remove Programs from the control panel.

### Install the client (ActiveX version)

- AliceStreet client software can be installed on demand. Simply use Internet Explorer on your desktop PC to navigate to the home page of the machine being used as the AliceStreet server and follow the instructions

# AliceStreet Conference Center

A **real** conference room on your desktop

- For example, if on your network you have called your AliceStreet server machine AliceStreet-server-01, go to:

<http://AliceStreet-server-01/>

- To operate correctly, the AliceStreet client requires Microsoft Windows with DirectX version 8.1 or higher
- To uninstall the client, use the shortcut in the AliceStreet installation directory

## Install the client (non Active X version)

- Contact your security or network administrator